zsh-autoenv

/via: https://github.com/Tarrasch/zsh-autoenv

configuration

- AUTOENV_FILE_ENTER: Name of the file to look for when entering directories. Default: .autoenv.zsh
- AUTOENV_FILE_LEAVE: Name of the file to look for when leaving directories. Requires AUTOENV_HANDLE_LEAVE=1.Default: .autoenv_leave.zsh
- AUTOENV_LOOK_UPWARDS: Look for zsh-autoenv «enter» files in parent dirs?. Default: 1
- AUTOENV_HANDLE_LEAVE: Handle leave events when changing away from a subtree, where an «enter» event was handled? Default: 1
- AUTOENV_DISABLED: (Temporarily) disable zsh-autoenv. This gets looked at in the chpwd handler. Default: 0
- AUTOENV_DEBUG: Set debug level. If enabled (> 0) it will print information to stderr.
    - 0: no debug messages
    - 1: generic debug logging
    - 2: more verbose messages messages about adding/removing files on the internal stack
    - 3: everything

sets xtrace option (set -x) while sourcing env files. Default: 0

usage

- `autoenv-edit`
    - $AUTOENV_EDITOR, $EDITOR, or vim for editing

help

- **autostash**:
    - sobreescribe una variable de entorno y la vuelve a dejar como estaba al salir
- **autoenv_source_parent**
    - ejecuta los ficheros **.autoenv.zsh** de los directorios superiores
    - opcionalmente podemos pasarle un parámetro `../..` para que solo ejecute ciertos niveles atrás ¿?
- **autoenv_append_path**: Appends path(s) to $path ($PATH), if they are not in there already.
- **autoenv_prepend_path**: Prepends path(s) to $path ($PATH), if they are not in there already.
- **autoenv_remove_path**: Removes path(s) from $path ($PATH).Returns 0 in case $path has changed, 1 otherwise.

azure example

/

```
autostash ARM_ACCESS_KEY=<key>
echo "auto environment enabled (infraestructure)"
```

/infrastructure

```
autoenv_source_parent ../..
az account set --subscription "XXX -PRO - Subscription"
echo "auto environment enabled (pro)"
```

/aks

```
autoenv_source_parent ../..
autostash ENV_SUBS="XXX - AKS - Subscription"
autostash ENV_RG="XXX-RG-AKS"
autostash ENV_AKS="XXX"
az account set --subscription "$ENV_SUBS"
az aks get-credentials --resource-group ${ENV_RG} --name ${ENV_AKS} --admin
echo "auto environment enabled ($ENV_SUBS)"
echo "aks credentials (${ENV_RG} - ${ENV_AKS})"
```

From:
https://matebcn.eu/ - **miguel angel torres egea**

Permanent link:
https://matebcn.eu/linux:zsh:oh-my-zsh:autoenv

Last update: **27/11/2024 12:20**